



HP iPAQ 6955 Easy Email Setup **(For Gmail e-mail service)**

Rogers makes setting up your wireless e-mail service quick and easy. Before beginning, please ensure you have everything you need to begin enjoying the time-saving benefits and convenience of sending and receiving wireless e-mail on the go.

Wireless E-mail Checklist:

E-mail-capable wireless device E-mail Plan ISP-based E-mail Address

STEP 1 Insert the SIM card and the battery into your wireless device

- **Charge your device for 20 minutes**

STEP 2 Turn on your wireless device

- **Ensure EDGE or GPRS appears on screen (indicates device is connected to the Rogers wireless network)**

STEP 3 Set up your wireless e-mail service

- **Follow these steps for [Gmail](#):**
 1. Log in to your Gmail account from your PC.
 2. Select **Settings** at the top of any Gmail page.
 3. Select the **Forwarding and POP** tab in the orange Mail Settings box.
 4. Under **POP Download**, choose to **Enable POP for all mail or Enable POP only for mail that arrives from now on**.
 5. Specify whether you want Gmail to keep a copy of messages in the Inbox when you access messages through POP.
 6. Select **Save Changes**.

Now you can **auto-configure Gmail** from your pocket pc:

1. On your pocket pc, press **Start** and scroll to **Messaging**.
2. Select **Menu -> Tools -> New Account**
3. Enter your e-mail address (i.e. [user@gmail.com](#)).
4. In the Auto Setup screen, wait until the status changes from **Connecting** to **Completed** and select **Next**.
5. Enter your name and e-mail user name.
6. Enter your password.
7. Check **Save password**, so you don't have to enter it every time you check e-mail and select **Next**.
8. Make sure that **Server Type** is set to **POP3** and select **Next**
9. Make sure that **Incoming Server** is set to **pop.gmail.com: 995**
10. Make sure that **Outgoing Server** is set to **smtp.rogerswirelessdata.com**
11. Leave Domain blank
12. Select Options
13. Select how often you want to receive your e-mail and ensure **Connection : The Internet** and select **Next**
14. Where it says, **Require SSL connection**, select **Yes** (check the box)
15. Where it says, **Outgoing server requires authentication**, select **No** (uncheck)

HP iPAQ 6955 Easy Email Setup

(For Gmail e-mail service)

- box) and select Next.
16. Select **Get message headers only** and check **Include 2kb of message body** (recommended)
 17. Select **Finish**.
 18. Select **Yes** to confirm that you would like to download mail for this new account now.

STEP 4 Begin sending e-mail

- **On your device, select Menu > Send / Receive**
- You may also access your mail account from your device using Internet Explorer. Go to <http://m.gmail.com>.

Need Help?

For free 24/7 technical support:

1 866 931-DATA (3282)

For online help, FAQs & user guides:

www.rogers.com/techsupport

For device-specific instructions:

Refer to your device's user guide

Wireless e-mail service requires an e-mail-capable wireless device activated on the Rogers Wireless network and a subscription to an E-mail Plan. For more information, visit www.rogers.com/wirelessemail.

TMTrademarks used under license. © 2007